

SLURM - Simple Linux Utility for Resource Management

Introduction

Slurm is an open source, fault-tolerant, and highly scalable cluster management and job scheduling system for large and small Linux clusters.

It provides three key functions:

- allocating exclusive and/or non-exclusive access to resources (computer nodes) to users for some duration of time so they can perform work,
- providing a framework for starting, executing, and monitoring work (typically a parallel job such as MPI) on a set of allocated nodes, and
- arbitrating contention for resources by managing a queue of pending jobs.



Installation

Controller name: slurm-ctrl

Install slurm-wlm and tools

```
ssh slurm-ctrl
apt install slurm-wlm slurm-wlm-doc mailutils mariadb-client mariadb-server
libmariadb-dev python-dev python-mysqldb
```

Install Maria DB Server

```
apt-get install mariadb-server
systemctl start mysql
mysql -u root
create database slurm_acct_db;
create user 'slurm'@'localhost';
set password for 'slurm'@'localhost' = password('slurmdbpass');
grant usage on *.* to 'slurm'@'localhost';
grant all privileges on slurm_acct_db.* to 'slurm'@'localhost';
flush privileges;
exit
```

In the file /etc/mysql/mariadb.conf.d/50-server.cnf we should have the following setting:

```
vi /etc/mysql/mariadb.conf.d/50-server.cnf
```

```
bind-address = localhost
```

Node Authentication

First, let us configure the default options for the munge service:

```
vi /etc/default/munge
OPTIONS="--syslog --key-file /etc/munge/munge.key"
```

Central Controller

The main configuration file is /etc/slurm-llnl/slurm.conf this file has to be present in the controller and *ALL* of the compute nodes and it also has to be consistent between all of them.

```
vi /etc/slurm-llnl/slurm.conf

#####
# /etc/slurm-llnl/slurm.conf
#####
# slurm.conf file generated by configurator easy.html.
# Put this file on all nodes of your cluster.
# See the slurm.conf man page for more information.
#
ControlMachine=slurm-ctrl
#ControlAddr=10.7.20.97
#
#MailProg=/bin/mail
Mpidefault=none
#Mpideparams=ports=#-#
ProctrackType=proctrack/pgid
ReturnToService=1
SlurmctldPidFile=/var/run/slurm-llnl/slurmctld.pid
##SlurmctldPidFile=/var/run/slurmctld.pid
#SlurmctldPort=6817
SlurmdPidFile=/var/run/slurm-llnl/slurmd.pid
##SlurmdPidFile=/var/run/slurmd.pid
#SlurmdPort=6818
SlurmdSpoolDir=/var/spool/slurmd
SlurmUser=slurm
#SlurmdUser=root
StateSaveLocation=/var/spool
SwitchType=switch/none
TaskPlugin=task/none
#
#
# TIMERS
#KillWait=30
#MinJobAge=300
```

```
#SlurmctldTimeout=120
#SlurmdTimeout=300
#
#
# SCHEDULING
FastSchedule=1
SchedulerType=sched/backfill
SelectType=select/linear
#SelectTypeParameters=
#
#
# LOGGING AND ACCOUNTING
AccountingStorageType=accounting_storage/none
ClusterName=cluster
#JobAcctGatherFrequency=30
JobAcctGatherType=jobacct_gather/none
#SlurmctldDebug=3
SlurmctldLogFile=/var/log/slurm-llnl/SlurmctldLogFile
#SlurmdDebug=3
SlurmdLogFile=/var/log/slurm-llnl/SlurmLogFile
#
#
# COMPUTE NODES
NodeName=linux1 NodeAddr=10.7.20.98 CPUs=1 State=UNKNOWN
```

Copy slurm.conf to compute nodes!

```
root@slurm-ctrl# scp /etc/slurm-llnl/slurm.conf csadmin@10.7.20.109:/tmp/.;
scp /etc/slurm-llnl/slurm.conf csadmin@10.7.20.110:/tmp/.
```

```
vi /lib/systemd/system/slurmctld.service
```

```
[Unit]
Description=Slurm controller daemon
After=network.target munge.service
ConditionPathExists=/etc/slurm-llnl/slurm.conf
Documentation=man:slurmctld(8)

[Service]
Type=forking
EnvironmentFile=-/etc/default/slurmctld
ExecStart=/usr/sbin/slurmctld $SLURMCTLD_OPTIONS
ExecStartPost=/bin/sleep 2
ExecReload=/bin/kill -HUP $MAINPID
PIDFile=/var/run/slurm-llnl/slurmctld.pid

[Install]
WantedBy=multi-user.target
```

```
vi /lib/systemd/system/slurmd.service
```

```
[Unit]
Description=Slurm node daemon
After=network.target munge.service
ConditionPathExists=/etc/slurm-llnl/slurm.conf
Documentation=man:slurmd(8)

[Service]
Type=forking
EnvironmentFile=-/etc/default/slurmd
ExecStart=/usr/sbin/slurmd $SLURMD_OPTIONS
ExecStartPost=/bin/sleep 2
ExecReload=/bin/kill -HUP $MAINPID
PIDFile=/var/run/slurm-llnl/slurmd.pid
KillMode=process
LimitNOFILE=51200
LimitMEMLOCK=infinity
LimitSTACK=infinity

[Install]
WantedBy=multi-user.target
```

```
root@slurm-ctrl# systemctl daemon-reload
root@slurm-ctrl# systemctl enable slurmdbd
root@slurm-ctrl# systemctl start slurmdbd
root@slurm-ctrl# systemctl enable slurmctld
root@slurm-ctrl# systemctl start slurmctld
```

Accounting Storage

After we have the slurm-llnl-slurmdbd package installed we configure it, by editing the /etc/slurm-llnl/slurmdbd.conf file:

```
vi /etc/slurm-llnl/slurmdbd.conf
```

```
#####
#
# /etc/slurm-llnl/slurmdbd.conf is an ASCII file which describes Slurm
# Database Daemon (SlurmDBD) configuration information.
# The contents of the file are case insensitive except for the names of
# nodes and files. Any text following a "#" in the configuration file is
# treated as a comment through the end of that line. The size of each
# line in the file is limited to 1024 characters. Changes to the
# configuration file take effect upon restart of SlurmDbd or daemon
# receipt of the SIGHUP signal unless otherwise noted.
#
# This file should be only on the computer where SlurmDBD executes and
# should only be readable by the user which executes SlurmDBD (e.g.
# "slurm"). This file should be protected from unauthorized access since
# it contains a database password.
```

```
#####
AuthType=auth/munge
AuthInfo=/var/run/munge/munge.socket.2
StorageHost=localhost
StoragePort=3306
StorageUser=slurm
StoragePass=slurmdbpass
StorageType=accounting_storage/mysql
StorageLoc=slurm_acct_db
LogFile=/var/log/slurm-llnl/slurmdbd.log
PidFile=/var/run/slurm-llnl/slurmdbd.pid
SlurmUser=slurm
```

```
root@slurm-ctrl# systemctl start slurmdbd
```

Authentication

Copy /etc/munge.key to all compute nodes

```
scp /etc/munge/munge.key csadmin@10.7.20.98:/tmp/.
```

Allow password-less access to slurm-ctrl

```
csadmin@slurm-ctrl:~$ ssh-copy-id -i .ssh/id_rsa.pub 10.7.20.102:
```

Run a job from slurm-ctrl

```
ssh csadmin@slurm-ctrl
srun -N 1 hostname
linux1
```

Test munge

```
munge -n | unmunge | grep STATUS
STATUS: Success (0)
munge -n | ssh slurm-ctrl unmunge | grep STATUS
STATUS: Success (0)
```

Test Slurm

```
sinfo
PARTITION AVAIL  TIMELIMIT  NODES  STATE NODELIST
debug*      up    infinite      1  idle  linux1
```

If computer node is **down** or **drain**

```
sinfo -a
```

```
PARTITION AVAIL  TIMELIMIT  NODES  STATE NODELIST
debug*        up    infinite     2  down  gpu[02-03]
```

sinfo

```
PARTITION AVAIL  TIMELIMIT  NODES  STATE NODELIST
gpu*        up    infinite     1  drain  gpu02
gpu*        up    infinite     1  down  gpu03
```

```
scontrol update nodename=gpu02 state=idle
scontrol update nodename=gpu03 state=idle
scontrol update nodename=gpu02 state=resume
```

sinfo -a

```
PARTITION AVAIL  TIMELIMIT  NODES  STATE NODELIST
debug*        up    infinite     2  idle  gpu[02-03]
```

Compute Nodes

A compute node is a machine which will receive jobs to execute, sent from the Controller, it runs the slurmd service.



Installation slurm and munge

```
ssh -l csadmin <compute-nodes> 10.7.20.109 10.7.20.110
sudo apt install slurm-wlm libmunge-dev libmunge2 munge
```

```
sudo vi /lib/systemd/system/slurmd.service
```

```
[Unit]
Description=Slurm node daemon
After=network.target munge.service
ConditionPathExists=/etc/slurm-llnl/slurm.conf
Documentation=man:slurmd(8)

[Service]
Type=forking
EnvironmentFile=-/etc/default/slurmd
ExecStart=/usr/sbin/slurmd $SLURMD_OPTIONS
ExecStartPost=/bin/sleep 2
ExecReload=/bin/kill -HUP $MAINPID
PIDFile=/var/run/slurm-llnl/slurmd.pid
KillMode=process
LimitNOFILE=51200
LimitMEMLOCK=infinity
LimitSTACK=infinity
```

```
[Install]
```

```
WantedBy=multi-user.target
```

```
sudo systemctl enable slurmd
sudo systemctl enable munge
sudo systemctl start slurmd
sudo systemctl start munge
```

Generate ssh keys

```
ssh-keygen
```

Copy ssh-keys to slurm-ctrl

```
ssh-copy-id -i ~/.ssh/id_rsa.pub csadmin@slurm-ctrl.inf.unibz.it:
```

Become root to do important things:

```
sudo -i
vi /etc/hosts
```

Add those lines below to the /etc/hosts file

```
10.7.20.97      slurm-ctrl.inf.unibz.it slurm-ctrl
10.7.20.98      linux1.inf.unibz.it    linux1
```

First copy the munge keys from the slurm-ctrl to all compute nodes, now fix location, owner and permission.

```
mv /tmp/munge.key /etc/munge/.
chown munge:munge /etc/munge/munge.key
chmod 400 /etc/munge/munge.key
```

Place /etc/slurm-llnl/slurm.conf in right place,

```
mv /tmp/slurm.conf /etc/slurm-llnl/
chown root: /etc/slurm-llnl/slurm.conf
```

Modify user accounts

Display the accounts created:

```
sacctmgr show account -s  # Show also associations in the accounts
sacctmgr show user -s
```

Add user

```
sacctmgr add user <username> Account=gpu-users Partition=gpu
```

Modify user, give 12000 minutes/200 hours for usage

```
sacctmgr modify user <username> set GrpTRESMin(cpu=12000,gres/gpu=12000)
```

Restart the services:

```
systemctl restart slurmctld.service  
systemctl restart slurmdbd.service
```

Check status:

```
systemctl status slurmctld.service  
systemctl status slurmdbd.service
```

Links

[Basic Configuration and Usage](#)

[Slurm Workload Manager Overview](#)

[Steps to create a small slurm cluster with GPU enabled nodes](#)

[Slurm in Ubuntu Clusters Part1](#)

[Slurm batch queueing system](#)

[SLURM Workload Manager](#)

[Slurm Quick Start Tutorial](#)

Linux Clusters Institute: Scheduling and Resource Management 2017

Modules

Add different python versions using spack!

1. First see which python versions are available:

```
root@slurm-ctrl:~# spack versions python  
==> Safe versions (already checksummed):  
3.8.2 3.7.7 3.7.4 3.7.1 3.6.7 3.6.4 3.6.1 3.5.2 3.4.10 3.2.6  
2.7.17 2.7.14 2.7.11 2.7.8  
3.8.1 3.7.6 3.7.3 3.7.0 3.6.6 3.6.3 3.6.0 3.5.1 3.4.3 3.1.5  
2.7.16 2.7.13 2.7.10  
3.8.0 3.7.5 3.7.2 3.6.8 3.6.5 3.6.2 3.5.7 3.5.0 3.3.6 2.7.18  
2.7.15 2.7.12 2.7.9
```

==> Remote versions (not yet checksummed):

3.10.0a6	3.8.7rc1	3.7.6rc1	3.6.8rc1	3.5.7rc1	3.4.9	3.4.0
3.1.2rc1	2.7.9rc1	2.6.6	2.4.5			
3.10.0a5	3.8.7				
...						
...						

2. now select the python version you would like to install:

```
root@slurm-ctrl:~# spack install python@3.8.2
==> 23834: Installing libiconv
==> Using cached archive: /opt/packages/spack/var/spack/cache/_source-
cache/archive/e6/e6a1b1b589654277ee790cce3734f07876ac4ccfaecbee8afa0b649cf52
9cc04.tar.gz
==> Staging archive: /tmp/root/spack-stage/spack-stage-libiconv-1.16-
b2wenwxf2widzewcvnhsxtjyisz3bcmc/libiconv-1.16.tar.gz
==> Created stage in /tmp/root/spack-stage/spack-stage-libiconv-1.16-
b2wenwxf2widzewcvnhsxtjyisz3bcmc
==> No patches needed for libiconv
==> 23834: libiconv: Building libiconv [AutotoolsPackage]
==> 23834: libiconv: Executing phase: 'autoreconf'
==> 23834: libiconv: Executing phase: 'configure'
==> 23834: libiconv: Executing phase: 'build'
==> 23834: libiconv: Executing phase: 'install'
==> 23834: libiconv: Successfully installed libiconv
Fetch: 0.04s. Build: 24.36s. Total: 24.40s.
[+] /opt/packages/spack/opt/spack/linux-ubuntu18.04-
skylake_avx512/gcc-9.3.0/libiconv-1.16-b2wenwxf2widzewcvnhsxtjyisz3bcmc
==> 23834: Installing libbsd
...
...
...
==> 23834: Installing python
==> Fetching https://www.python.org/ftp/python/3.8.2/Python-3.8.2.tgz
#####
##### 100.0%
==> Staging archive: /tmp/root/spack-stage/spack-stage-python-3.8.2-
vmyztzplzddt2arrsx7d7koebyuzvk6s/Python-3.8.2.tgz
==> Created stage in /tmp/root/spack-stage/spack-stage-python-3.8.2-
vmyztzplzddt2arrsx7d7koebyuzvk6s
==> Ran patch() for python
==> 23834: python: Building python [AutotoolsPackage]
==> 23834: python: Executing phase: 'autoreconf'
==> 23834: python: Executing phase: 'configure'
==> 23834: python: Executing phase: 'build'
==> 23834: python: Executing phase: 'install'
==> 23834: python: Successfully installed python
Fetch: 1.81s. Build: 1m 42.11s. Total: 1m 43.91s.
[+] /opt/packages/spack/opt/spack/linux-ubuntu18.04-
skylake_avx512/gcc-9.3.0/python-3.8.2-vmyztzplzddt2arrsx7d7koebyuzvk6s
```

This will take some minutes time, depending on the type of version

3. Now you need to add a modules file

```
root@slurm-ctrl:~# vi /opt/modules/modulefiles/python-3.8.2
```

```
##%Module1.0
proc ModulesHelp { } {
    global dotversion
    puts stderr "\tPython 3.8.2"
}

module-whatis "Python 3.8.2"

set main_root      /opt/packages/spack/opt/spack/linux-ubuntu18.04-
skylake_avx512/gcc-9.3.0/python-3.8.2-vmyztzplzddt2arrsx7d7koebyuzvk6s
setalias python3.8      /opt/packages/spack/opt/spack/linux-
ubuntu18.04-skylake_avx512/gcc-9.3.0/python-3.8.2-
vmyztzplzddt2arrsx7d7koebyuzvk6s/bin/python3.8

prepend-path PATH $main_root/bin
prepend-path LIBRARY_PATH $main_root/lib
```

4. New module should now be available:

```
root@slurm-ctrl:~# module avail
----- /opt/modules/modulefiles -----
-----
anaconda3  cuda-11.2.1  intel-mpi          module-info  py-mpi4py
python-3.7.7        use.own
bzip      dot          intel-mpi-benchmarks  modules      python-2.7.18
python-3.8.2
cuda-10.2  gcc-6.5.0   miniconda3        null         python-3.5.7
python-3.9.2
cuda-11.0  go-1.15.3   module-git        openmpi      python-3.6.10
singularity-3.6.4
```

5. Load the new module

```
root@slurm-ctrl:~# module load python-3.8.2
```

6. Verify it works

```
root@slurm-ctrl:~# python3.8
Python 3.8.2 (default, Mar 19 2021, 11:05:37)
[GCC 9.3.0] on linux
Type "help", "copyright", "credits" or "license" for more information.
>>> exit()
```

7. Unload the new module

```
module unload python-3.8.2
```

Python

Python 3.7.7

```
cd /opt/packages
mkdir /opt/packages/python/3.7.7
wget https://www.python.org/ftp/python/3.7.7/Python-3.7.7.tar.xz
tar xfJ Python-3.7.7.tar.xz
cd Python-3.7.7/
./configure --prefix=/opt/packages/python/3.7.7/ --enable-optimizations
make
make install
```

Python 2.7.18

```
cd /opt/packages
mkdir /opt/packages/python/2.7.18
wget https://www.python.org/ftp/python/2.7.18/Python-2.7.18.tar.xz
cd Python-2.7.18
./configure --prefix=/opt/packages/python/2.7.18/ --enable-optimizations
make
make install
```

Create modules file

PYTHON

```
cd /opt/modules/modulefiles/
vi python-2.7.18
```

```
#%Module1.0
proc ModulesHelp { } {
    global dotversion

    puts stderr "\tPython 2.7.18"
}

module-whatis "Python 2.7.18"
prepend-path PATH /opt/packages/python/2.7.18/bin
```

CUDA

```
vi /opt/modules/modulefiles/cuda-10.2
```

```
##Module1.0
proc ModulesHelp { } {
    global dotversion

    puts stderr "\tcuda-10.2"
}

module-whatis "cuda-10.2"

set      prefix  /usr/local/cuda-10.2

setenv    CUDA_HOME      $prefix
prepend-path PATH          $prefix/bin
prepend-path LD_LIBRARY_PATH $prefix/lib64
```

GCC

This takes a long time!

Commands to run to compile gcc-6.1.0

```
wget https://ftp.gnu.org/gnu/gcc/gcc-6.1.0/gcc-6.1.0.tar.bz2
tar xfj gcc-6.1.0.tar.bz2
cd gcc-6.1.0
./contrib/download_prerequisites
./configure --prefix=/opt/package/gcc/6.1.0 --disable-multilib
make
```

After some time an error occurs, and the make process stops!

```
...
In file included from ../../libgcc/unwind-dw2.c:401:0:
./md-unwind-support.h: In function 'x86_64_fallback_frame_state':
./md-unwind-support.h:65:47: error: dereferencing pointer to incomplete type
'struct ucontext'
        sc = (struct sigcontext *) (void *) &uc_->uc_mcontext;
                                         ^
...
../../libgcc/shared-object.mk:14: recipe for target 'unwind-dw2.o' failed
```

To fix do: [solution](#)

```
vi /opt/packages/gcc-6.1.0/x86_64-pc-linux-gnu/libgcc/md-unwind-support.h
```

and replace/comment out line 61 with this:

```
struct ucontext_t *uc_ = context->cfa;
```

old line: /* struct ucontext *uc_ = context->cfa; */

```
make
```

Next error:

```
../../../../libsanitizer/sanitizer_common/sanitizer_stoptheworld_linux_libcde
p.cc:270:22: error: aggregate 'sigaltstack handler_stack' has incomplete
type and cannot be defined
    struct sigaltstack handler_stack;
```

To fix see: [solution](#) or https://gcc.gnu.org/bugzilla/show_bug.cgi?id=81066

Amend the files according to solution above!

Next error:

```
...
checking for unzip... unzip
configure: error: cannot find neither zip nor jar, cannot continue
Makefile:23048: recipe for target 'configure-target-libjava' failed
...
...
```

```
apt install unzip zip
```

and run make again!

```
make
```

Next error:

```
...
In file included from ../.././libjava/prims.cc:26:0:
../.././libjava/prims.cc: In function 'void _Jv_catch_fpe(int, siginfo_t*, void*)':
./include/java-signal.h:32:26: error: invalid use of incomplete type 'struct
_Jv_catch_fpe(int, siginfo_t*, void*):>ucontext'
    gregset_t &_gregs = _uc->uc_mcontext.gregs;      \
...
...
```

Edit the file: /opt/packages/gcc-6.1.0/x86_64-pc-linux-gnu/libjava/include/java-signal.h

```
vi /opt/packages/gcc-6.1.0/x86_64-pc-linux-gnu/libjava/include/java-signal.h
```

Not enough more errors!

```
// kh
  ucontext_t *_uc = (ucontext_t *);                                \
  //struct ucontext *_uc = (struct ucontext *)_p;
\
// kh
```

Next error:

```
...
In file included from ../.././libjava/prims.cc:26:0:
./include/java-signal.h:32:3: warning: multi-line comment [-Wcomment]
  //struct ucontext *_uc = (struct ucontext *)_p;    \
  ^
../.././libjava/prims.cc: In function 'void _Jv_catch_fpe(int, siginfo_t*, void*)':
./include/java-signal.h:31:15: warning: unused variable '_uc' [-Wunused-variable]
  ucontext_t *_uc = (ucontext_t *)_p;      \
  ^
../.././libjava/prims.cc:192:3: note: in expansion of macro
'HANDLE_DIVIDE_OVERFLOW'
  HANDLE_DIVIDE_OVERFLOW;
  ^~~~~~
../.././libjava/prims.cc:203:1: error: expected 'while' before 'jboolean'
jboolean
^~~~~~
../.././libjava/prims.cc:203:1: error: expected '(' before 'jboolean'
../.././libjava/prims.cc:204:1: error: expected primary-expression before
'_Jv_equalUtf8Consts'
  _Jv_equalUtf8Consts (const Utf8Const* a, const Utf8Const *b)
  ^~~~~~
../.././libjava/prims.cc:204:1: error: expected ')' before
'_Jv_equalUtf8Consts'
../.././libjava/prims.cc:204:1: error: expected ';' before
'_Jv_equalUtf8Consts'
../.././libjava/prims.cc:204:22: error: expected primary-expression before
'const'
  _Jv_equalUtf8Consts (const Utf8Const* a, const Utf8Const *b)
...
...
```

Examples

Example mnist

An simple example to use nvidia GPU!

The example consists of the following files:

- README.md
- requirements.txt
- main.job
- main.py

Create a folder mnist and place the 4 files in there.

```
mkdir mnist
```

```
cat README.md
```

```
# Basic MNIST Example

```bash
pip install -r requirements.txt
python main.py
CUDA_VISIBLE_DEVICES=2 python main.py # to specify GPU id to ex. 2
```

```

```
cat requirements.txt
```

```
torch
torchvision
```

```
cat main.job
```

```
#!/bin/bash

#SBATCH --job-name=mnist
#SBATCH --output=mnist.out
#SBATCH --error=mnist.err

#SBATCH --partition gpu
#SBATCH --gres=gpu
#SBATCH --mem-per-cpu=4gb
#SBATCH --nodes 2
#SBATCH --time=00:08:00

#SBATCH --ntasks=10

#SBATCH --mail-type=ALL
#SBATCH --mail-user=<your-email@address.com>

ml load miniconda3
python3 main.py
```

Remove your-email@address.com and add your e-mail address.

[main.py](#)

```
from __future__ import print_function
import argparse
import torch
import torch.nn as nn
import torch.nn.functional as F
import torch.optim as optim
from torchvision import datasets, transforms
from torch.optim.lr_scheduler import StepLR

class Net(nn.Module):
    def __init__(self):
        super(Net, self).__init__()
        self.conv1 = nn.Conv2d(1, 32, 3, 1)
        self.conv2 = nn.Conv2d(32, 64, 3, 1)
        self.dropout1 = nn.Dropout2d(0.25)
        self.dropout2 = nn.Dropout2d(0.5)
        self.fc1 = nn.Linear(9216, 128)
        self.fc2 = nn.Linear(128, 10)

    def forward(self, x):
        x = self.conv1(x)
        x = F.relu(x)
        x = self.conv2(x)
        x = F.max_pool2d(x, 2)
        x = self.dropout1(x)
        x = torch.flatten(x, 1)
        x = self.fc1(x)
        x = F.relu(x)
        x = self.dropout2(x)
        x = self.fc2(x)
        return x
```

```

= self.fc1(x) x = F.relu(x) x = self.dropout2(x) x = self.fc2(x) output = F.log_softmax(x, dim=1)
return output def train(args, model, device, train_loader, optimizer, epoch): model.train() for
batch_idx, (data, target) in enumerate(train_loader): data, target = data.to(device),
target.to(device) optimizer.zero_grad() output = model(data) loss = F.nll_loss(output, target)
loss.backward() optimizer.step() if batch_idx % args.log_interval == 0: print('Train Epoch: {}'
[{} / {} ({:.0f}%)]\tLoss: {:.6f}'.format( epoch, batch_idx * len(data), len(train_loader.dataset),
100. * batch_idx / len(train_loader), loss.item())) def test(args, model, device, test_loader):
model.eval() test_loss = 0 correct = 0 with torch.no_grad(): for data, target in test_loader: data,
target = data.to(device), target.to(device) output = model(data) test_loss += F.nll_loss(output,
target, reduction='sum').item() # sum up batch loss pred = output.argmax(dim=1,
keepdim=True) # get the index of the max log-probability correct +=
pred.eq(target.view_as(pred)).sum().item() test_loss /= len(test_loader.dataset) print("\nTest
set: Average loss: {:.4f}, Accuracy: {} / {} ({:.0f}%)\n".format( test_loss, correct,
len(test_loader.dataset), 100. * correct / len(test_loader.dataset))) def main(): # Training
settings parser = argparse.ArgumentParser(description='PyTorch MNIST Example')
parser.add_argument('--batch-size', type=int, default=64, metavar='N', help='input batch size
for training (default: 64)') parser.add_argument('--test-batch-size', type=int, default=1000,
metavar='N', help='input batch size for testing (default: 1000)') parser.add_argument('--'
epochs', type=int, default=14, metavar='N', help='number of epochs to train (default: 14)')
parser.add_argument('--lr', type=float, default=1.0, metavar='LR', help='learning rate (default:
1.0)') parser.add_argument('--gamma', type=float, default=0.7, metavar='M', help='Learning
rate step gamma (default: 0.7)') parser.add_argument('--no-cuda', action='store_true',
default=False, help='disables CUDA training') parser.add_argument('--seed', type=int,
default=1, metavar='S', help='random seed (default: 1)') parser.add_argument('--log-interval',
type=int, default=10, metavar='N', help='how many batches to wait before logging training
status') parser.add_argument('--save-model', action='store_true', default=False, help='For
Saving the current Model') args = parser.parse_args() use_cuda = not args.no_cuda and
torch.cuda.is_available() torch.manual_seed(args.seed) device = torch.device("cuda" if
use_cuda else "cpu") kwargs = {'num_workers': 1, 'pin_memory': True} if use_cuda else {}
train_loader = torch.utils.data.DataLoader( datasets.MNIST('..../data', train=True,
download=True, transform=transforms.Compose([ transforms.ToTensor(),
transforms.Normalize((0.1307,), (0.3081,)) ])), batch_size=args.batch_size, shuffle=True,
**kwargs) test_loader = torch.utils.data.DataLoader( datasets.MNIST('..../data', train=False,
transform=transforms.Compose([ transforms.ToTensor(), transforms.Normalize((0.1307,),
(0.3081,)) ])), batch_size=args.test_batch_size, shuffle=True, **kwargs) model =
Net().to(device) optimizer = optim.Adadelta(model.parameters(), lr=args.lr) scheduler =
StepLR(optimizer, step_size=1, gamma=args.gamma) for epoch in range(1, args.epochs + 1):
train(args, model, device, train_loader, optimizer, epoch) test(args, model, device, test_loader)
scheduler.step() if args.save_model: torch.save(model.state_dict(), "mnist_cnn.pt") if __name__ ==
'__main__': main()

```

- 1.
- 2.
3. from __future__ import print_function
4. import argparse
5. import torch
6. import torch.nn as nn
7. import torch.nn.functional as F
8. import torch.optim as optim
9. from torchvision import datasets, transforms
10. from torch.optim.lr_scheduler import StepLR
- 11.

```
12.
13. class Net(nn.Module):
14.     def __init__(self):
15.         super(Net, self).__init__()
16.         self.conv1 = nn.Conv2d(1, 32, 3, 1)
17.         self.conv2 = nn.Conv2d(32, 64, 3, 1)
18.         self.dropout1 = nn.Dropout2d(0.25)
19.         self.dropout2 = nn.Dropout2d(0.5)
20.         self.fc1 = nn.Linear(9216, 128)
21.         self.fc2 = nn.Linear(128, 10)
22.
23.     def forward(self, x):
24.         x = self.conv1(x)
25.         x = F.relu(x)
26.         x = self.conv2(x)
27.         x = F.max_pool2d(x, 2)
28.         x = self.dropout1(x)
29.         x = torch.flatten(x, 1)
30.         x = self.fc1(x)
31.         x = F.relu(x)
32.         x = self.dropout2(x)
33.         x = self.fc2(x)
34.         output = F.log_softmax(x, dim=1)
35.         return output
36.
37.
38. def train(args, model, device, train_loader, optimizer, epoch):
39.     model.train()
40.     for batch_idx, (data, target) in enumerate(train_loader):
41.         data, target = data.to(device), target.to(device)
42.         optimizer.zero_grad()
43.         output = model(data)
44.         loss = F.nll_loss(output, target)
45.         loss.backward()
46.         optimizer.step()
47.         if batch_idx % args.log_interval == 0:
48.             print('Train Epoch: {} [{}/{} ({:.0f}%)]\tLoss: {:.6f}'.format(
49.                 epoch, batch_idx * len(data), len(train_loader.dataset),
50.                 100. * batch_idx / len(train_loader), loss.item()))
51.
52.
53. def test(args, model, device, test_loader):
54.     model.eval()
55.     test_loss = 0
56.     correct = 0
57.     with torch.no_grad():
58.         for data, target in test_loader:
59.             data, target = data.to(device), target.to(device)
60.             output = model(data)
61.             test_loss += F.nll_loss(output, target,
62.                                    reduction='sum').item() # sum up batch loss
63.             pred = output.argmax(dim=1, keepdim=True) # get the index
64.             # of the max log-probability
65.             correct += pred.eq(target.view_as(pred)).sum().item()
```

```
65.     test_loss /= len(test_loader.dataset)
66.
67.     print('\nTest set: Average loss: {:.4f}, Accuracy: {}/{}
68.           {:.0f}%\n'.format(
69.             test_loss, correct, len(test_loader.dataset),
70.             100. * correct / len(test_loader.dataset)))
71.
72. def main():
73.     # Training settings
74.     parser = argparse.ArgumentParser(description='PyTorch MNIST
Example')
75.     parser.add_argument('--batch-size', type=int, default=64,
metavar='N',
76.                         help='input batch size for training (default:
64)')
77.     parser.add_argument('--test-batch-size', type=int, default=1000,
metavar='N',
78.                         help='input batch size for testing (default:
1000)')
79.     parser.add_argument('--epochs', type=int, default=14, metavar='N',
80.                         help='number of epochs to train (default: 14)')
81.     parser.add_argument('--lr', type=float, default=1.0, metavar='LR',
82.                         help='learning rate (default: 1.0)')
83.     parser.add_argument('--gamma', type=float, default=0.7, metavar='M',
84.                         help='Learning rate step gamma (default: 0.7)')
85.     parser.add_argument('--no-cuda', action='store_true', default=False,
86.                         help='disables CUDA training')
87.     parser.add_argument('--seed', type=int, default=1, metavar='S',
88.                         help='random seed (default: 1)')
89.     parser.add_argument('--log-interval', type=int, default=10,
metavar='N',
90.                         help='how many batches to wait before logging
training status')
91.
92.     parser.add_argument('--save-model', action='store_true',
default=False,
93.                         help='For Saving the current Model')
94.     args = parser.parse_args()
95.     use_cuda = not args.no_cuda and torch.cuda.is_available()
96.
97.     torch.manual_seed(args.seed)
98.
99.     device = torch.device("cuda" if use_cuda else "cpu")
100.
101.    kwargs = {'num_workers': 1, 'pin_memory': True} if use_cuda else {}
102.    train_loader = torch.utils.data.DataLoader(
103.        datasets.MNIST('../data', train=True, download=True,
104.                      transform=transforms.Compose([
105.                          transforms.ToTensor(),
106.                          transforms.Normalize((0.1307,), (0.3081,)))
107.                      ])),
108.        batch_size=args.batch_size, shuffle=True, **kwargs)
109.    test_loader = torch.utils.data.DataLoader(
110.        datasets.MNIST('../data', train=False,
transform=transforms.Compose([
```

```

111.                 transforms.ToTensor(),
112.                 transforms.Normalize((0.1307,), (0.3081,)))
113.             ])),
114.             batch_size=args.test_batch_size, shuffle=True, **kwargs)
115.
116.         model = Net().to(device)
117.         optimizer = optim.Adadelta(model.parameters(), lr=args.lr)
118.
119.         scheduler = StepLR(optimizer, step_size=1, gamma=args.gamma)
120.         for epoch in range(1, args.epochs + 1):
121.             train(args, model, device, train_loader, optimizer, epoch)
122.             test(args, model, device, test_loader)
123.             scheduler.step()
124.
125.         if args.save_model:
126.             torch.save(model.state_dict(), "mnist_cnn.pt")
127.
128.
129. if __name__ == '__main__':
130.     main()
131.
132.

```

Once you have all files launch this command on slurm-ctrl:

```
sbatch main.job
```

Check your job with

```
squeue
```

CUDA NVIDIA TESLA Infos

nvidia-smi

```
root@gpu02:~# watch nvidia-smi
```

```
Every 2.0s: nvidia-smi                                         gpu02: Mon
Jun 22 17:49:14 2020

Mon Jun 22 17:49:14 2020
+-----+
--+
| NVIDIA-SMI 440.64.00      Driver Version: 440.64.00      CUDA Version: 10.2
|
|-----+-----+-----+
--+
| GPU  Name      Persistence-M| Bus-Id      Disp.A | Volatile Uncorr.
```

```

ECC |
| Fan Temp Perf Pwr:Usage/Cap| Memory-Usage | GPU-Util Compute
M. |
|=====+=====+=====+
==|
| 0 Tesla V100-PCIE... On | 00000000:3B:00.0 Off |
0 |
| N/A 53C P0 139W / 250W | 31385MiB / 32510MiB | 69%
Default |
+-----+-----+-----+
--+
| 1 Tesla V100-PCIE... On | 00000000:AF:00.0 Off |
0 |
| N/A 35C P0 26W / 250W | 0MiB / 32510MiB | 0%
Default |
+-----+-----+-----+
--+
+-----+
--+
| Processes: GPU
Memory |
| GPU PID Type Process name Usage
|
|=====+=====+
==|
| 0 8627 C /opt/anaconda3/bin/python3
31373MiB |
+-----+
--+

```

deviceQuery

To run the deviceQuery it is necessary to make it first!

```

root@gpu03:~# cd /usr/local/cuda/samples/1_Utils/deviceQuery
make

```

Add PATH to the system wide environment

```

vi /etc/environment

```

Add this to the end

```

/usr/local/cuda/samples/bin/x86_64/linux/release

```

Next enable/source it:

```

source /etc/environment

```

```
root@gpu03:~# deviceQuery
deviceQuery Starting...
```

CUDA Device Query (Runtime API) version (CUDART static linking)

Detected 2 CUDA Capable device(s)

Device 0: "Tesla V100-PCIE-32GB"

| | |
|--|----------------------------|
| CUDA Driver Version / Runtime Version | 10.2 / 10.2 |
| CUDA Capability Major/Minor version number: | 7.0 |
| Total amount of global memory:
bytes) | 32510 MBytes (34089730048 |
| (80) Multiprocessors, (64) CUDA Cores/MP: | 5120 CUDA Cores |
| GPU Max Clock rate: | 1380 MHz (1.38 GHz) |
| Memory Clock rate: | 877 Mhz |
| Memory Bus Width: | 4096-bit |
| L2 Cache Size: | 6291456 bytes |
| Maximum Texture Dimension Size (x,y,z)
65536), 3D=(16384, 16384, 16384) | 1D=(131072), 2D=(131072, |
| Maximum Layered 1D Texture Size, (num) layers | 1D=(32768), 2048 layers |
| Maximum Layered 2D Texture Size, (num) layers
layers | 2D=(32768, 32768), 2048 |
| Total amount of constant memory: | 65536 bytes |
| Total amount of shared memory per block: | 49152 bytes |
| Total number of registers available per block: | 65536 |
| Warp size: | 32 |
| Maximum number of threads per multiprocessor: | 2048 |
| Maximum number of threads per block: | 1024 |
| Max dimension size of a thread block (x,y,z): | (1024, 1024, 64) |
| Max dimension size of a grid size (x,y,z): | (2147483647, 65535, 65535) |
| Maximum memory pitch: | 2147483647 bytes |
| Texture alignment: | 512 bytes |
| Concurrent copy and kernel execution: | Yes with 7 copy engine(s) |
| Run time limit on kernels: | No |
| Integrated GPU sharing Host Memory: | No |
| Support host page-locked memory mapping: | Yes |
| Alignment requirement for Surfaces: | Yes |
| Device has ECC support: | Enabled |
| Device supports Unified Addressing (UVA): | Yes |
| Device supports Compute Preemption: | Yes |
| Supports Cooperative Kernel Launch: | Yes |
| Supports MultiDevice Co-op Kernel Launch: | Yes |
| Device PCI Domain ID / Bus ID / location ID: | 0 / 59 / 0 |
| Compute Mode:
< Default (multiple host threads can use ::cudaSetDevice() with device
simultaneously) > | |

Device 1: "Tesla V100-PCIE-32GB"

| | |
|---|---------------------------|
| CUDA Driver Version / Runtime Version | 10.2 / 10.2 |
| CUDA Capability Major/Minor version number: | 7.0 |
| Total amount of global memory: | 32510 MBytes (34089730048 |

bytes)

| | |
|---|--|
| (80) Multiprocessors, (64) CUDA Cores/MP: | 5120 CUDA Cores |
| GPU Max Clock rate: | 1380 MHz (1.38 GHz) |
| Memory Clock rate: | 877 Mhz |
| Memory Bus Width: | 4096-bit |
| L2 Cache Size: | 6291456 bytes |
| Maximum Texture Dimension Size (x,y,z) | 1D=(131072), 2D=(131072, 65536), 3D=(16384, 16384, 16384) |
| Maximum Layered 1D Texture Size, (num) layers | 1D=(32768), 2048 layers |
| Maximum Layered 2D Texture Size, (num) layers | 2D=(32768, 32768), 2048 layers |
| Total amount of constant memory: | 65536 bytes |
| Total amount of shared memory per block: | 49152 bytes |
| Total number of registers available per block: | 65536 |
| Warp size: | 32 |
| Maximum number of threads per multiprocessor: | 2048 |
| Maximum number of threads per block: | 1024 |
| Max dimension size of a thread block (x,y,z): | (1024, 1024, 64) |
| Max dimension size of a grid size (x,y,z): | (2147483647, 65535, 65535) |
| Maximum memory pitch: | 2147483647 bytes |
| Texture alignment: | 512 bytes |
| Concurrent copy and kernel execution: | Yes with 7 copy engine(s) |
| Run time limit on kernels: | No |
| Integrated GPU sharing Host Memory: | No |
| Support host page-locked memory mapping: | Yes |
| Alignment requirement for Surfaces: | Yes |
| Device has ECC support: | Enabled |
| Device supports Unified Addressing (UVA): | Yes |
| Device supports Compute Preemption: | Yes |
| Supports Cooperative Kernel Launch: | Yes |
| Supports MultiDevice Co-op Kernel Launch: | Yes |
| Device PCI Domain ID / Bus ID / location ID: | 0 / 175 / 0 |
| Compute Mode: | < Default (multiple host threads can use ::cudaSetDevice() with device simultaneously) > |
| > Peer access from Tesla V100-PCIE-32GB (GPU0) -> Tesla V100-PCIE-32GB (GPU1) : | Yes |
| > Peer access from Tesla V100-PCIE-32GB (GPU1) -> Tesla V100-PCIE-32GB (GPU0) : | Yes |
| deviceQuery, CUDA Driver = CUDART, CUDA Driver Version = 10.2, CUDA Runtime Version = 10.2, NumDevs = 2 | |
| Result = PASS | |

Links

<https://www.admin-magazine.com/HPC/Articles/Warewulf-Cluster-Manager-Development-and-Run-Time/Warewulf-3-Code/MPICH2>

https://proteusmaster.urcf.drexel.edu/urcfwiki/index.php/Environment_Modules_Quick_Start_Guide

[https://en.wikipedia.org/wiki/Environment_Modules_\(software\)](https://en.wikipedia.org/wiki/Environment_Modules_(software))

<http://www.walkingrandomly.com/?p=5680>

<https://modules.readthedocs.io/en/latest/index.html>

From:

<https://wiki.inf.unibz.it/> - **Engineering-Tech Wiki**



Permanent link:

<https://wiki.inf.unibz.it/doku.php?id=tech:slurm&rev=1617023924>

Last update: **2021/03/29 15:18**